### If you are trying to connect a new computer to your network:

- 1. If the computer is wireless, connect to your router using the "Wireless Settings" listed on the back of this sheet.
  - a. Search for wireless networks to find your SSID. Connect to it and enter the password when prompted.
- 2. If the computer is to be wired, connect a cat5 cable from the computer to an available LAN port on your router.
  - a. Verify that the corresponding port light on the router is illuminated.

### Follow these steps in the event of an internet service interruption:

#### 1. Verify that all devices are powered on:

- a. The antenna power adapter has a light (white or green) to indicate it is powered on.
- b. Your router and phone adapter have lights indicating their operation.

### 2. Reboot your equipment in the following order:

- a. Unplug the power to the antenna power adapter, wait 3 seconds, and plug it back in.
- b. If applicable, unplug the power to the phone adapter, wait 3 seconds, and plug it back in.
- c. Unplug the power to the router, wait 3 seconds, and plug it back in.
- d. Restart your computer.

### 3. Verify that all CAT5 cables are properly plugged in:

- a. Verify that the antenna power adapter has two cat5 cables plugged into it. The POE port of the power adapter must be connected to the wiring going outside (antenna) and the LAN port must be connected to the phone adapter (if present) or your router.
- b. If you have a phone adapter, make sure its Internet port is plugged into the LAN port of the antenna power adapter. Otherwise, make sure your router's Internet/WAN port is plugged into the LAN port of the power adapter.
- c. Consult the customer wiring diagram shown below.

### 4. Verify that your router settings are correct:

- a. Configure your router using the "Router Configuration" information listed on the back of this sheet.
- 5. Contact Kayenta Technologies customer support at 435-668-6083.



# **Customer Information Setup Sheet**

Equipment Locations	ins
Antonno Douror Cunnlur	
Antenna Power Supply:	zppiy:
Router:	outer:
Phone Adapter:	apter:

## **Router Configuration:**

From time to time, it may be necessary to access your router in order to change or restore its configuration settings. Unless otherwise specified in a service contract, the router is the customer's personal equipment; it is the customer's sole responsibility to manage their own router!

Open a web browser and type in your router's IP address. It may prompt you to enter a username and password. Default login information for common routers:

Linksys	IP Address: 192.168.1.1	Username: admin	Password: admin
Netgear	IP Address: 192.168.0.1 or 192.168.1.1	Username: admin	Password: password
D-Link	IP Address: 192.168.0.1	Username: admin	Password: password
Belkin	IP Address: 192.168.2.1	Username: admin	Password: <blank></blank>
Asus	IP Address: 192.168.1.1 or 192.168.50.1	Username: admin	Password: password
	.inksys Vetgear D-Link Belkin Asus	inksysIP Address: 192.168.1.1VetgearIP Address: 192.168.0.1 or 192.168.1.1O-LinkIP Address: 192.168.0.1BelkinIP Address: 192.168.2.1AsusIP Address: 192.168.1.1 or 192.168.50.1	inksysIP Address: 192.168.1.1Username: adminVetgearIP Address: 192.168.0.1 or 192.168.1.1Username: adminO-LinkIP Address: 192.168.0.1Username: adminBelkinIP Address: 192.168.2.1Username: adminAsusIP Address: 192.168.1.1 or 192.168.50.1Username: admin

#### **Router Information** (if not default - see above)

Local IP Address:	Username:	Password:	

Static IP Settings			
Static IP Address:	Subnet Mask:	Gateway:	
Primary DNS:	Secondary DNS:		

PPPoE Settings		
Username:	Password:	

Wireless Settings		
SSID:	WPA Password:	

# **Other Information**

## Kayenta Technologies Contact Information:

Website	Billing Portal	Email	Phone
www.kayenta.net	ucrm.kayenta.net	support@kayenta.net	(435) 668-6083